



Parachute Top F201



DESIGNED BY
**Sharon
Sorken**

Materials

- 4 skeins Artyarns Silk Pearl
- size 7 needles
- size G crochet hook

Instructions

Note: You may choose to cast on with a contrasting waste yarn and knit a row. After assembling the Parachute top you can crochet the edge off of the waste yarn. This will allow the top to open and stretch.

Gauge: approximately 20 sts over 4" (this is an open lace pattern and has quite a bit of stretch)

One size fits all (length 14", width 32")

Glossary

K-knit

K2 tog-knit 2 stitches together

Yo-yarn over

Ssk-slip one stitch, knit one stitch, pass slip stitch over the knit stitch

Lace Pattern

Pattern is worked over an even number of stitches.

Row 1 (RS) K1,* yo, k2tog, repeat from *, k1

Row 2, 4 (WS) Purl

Row 3 K1, *skp, yo, repeat from *, k1

Artyarns™

39 Westmoreland Avenue White Plains New York 10606 914.428.0333 artyarns.com

©2010 by Iris Schreier. No copies may be made without written permission.

F201
Page 1 of 2



Parachute Top

Back

Cast on 140 sts loosely. Knit in stockinette for two rows. Begin lace pattern. Work for 120 rows (60 lace holes) or 14.” Place stitches on holder.

Front

Work same as for back. When piece measures 12 “ (row 108) begin neck

Neck

Cast off loosely center 30 sts. Attach another ball of yarn and decrease as follows:
Bind off 1 sts at each side of neck edge every other row 6 times.

Finishing

Join front to back with a three needle bind off. Bind off 49 sts for shoulder, bind off 42 sts for back neck, bind off 49 for shoulder. Sew side seams allowing an 8 “ opening for armhole front and back. Single-crochet around armhole for 2 rows. Single-crochet around neck edge for one row. Single-crochet around bottom edge for two rows.